

PROCORE INTEGRATION


Enabling the Procore Integration

MSite's **integration** with **Procore** streamlines workforce management and simplifies reporting for site teams.


How to enable integration

1. To enable the **Procore Integration**, go to the toolbar on the left. Then select **System** followed by **Integrations**.

Clicking on **Integrations** should display a dropdown, from here, select the **Procore** option.



2. On the **Procore Integration** page, you will be required to enter the **Vendor ID**, this may also be referred to as the **Procore Company ID**. *You will be able to find this in your **Procore system**.*

A screenshot of the 'Procore' integration setup page. At the top, there is a green gear icon and the word 'Procore'. Below this, there is a 'Vendor ID' field with the value '598134325513661' entered. The field is circled in orange. Below the Vendor ID field, there is a 'Worker Sync' section. It contains a 'Click Sync Workers Now' button and a list of conditions: 'are associated to active sites which are mapped to a project in Procore' and 'do not already have a Procore Worker ID'. There is a 'Sync Workers Now' button. Below this, there is a 'Timecard Sync' section. It contains a 'Timecard Sync' checkbox which is checked, and a description: 'Uses MSite shift data (FILO) to create Timecard entries in Procore. FILO is a method of calculating shift length using First In and Last Out timestamps per worker, therefore ignoring breaks'. At the bottom right, there are 'Cancel' and 'Save' buttons.

Once you have entered your **Vendor ID** and select the **Save** button, the integration should now be **active**.



PROCORE INTEGRATION

Enabling the Procore Integration

How to enable integration

3. Syncing Workers from MSite to Procore

As part of the integration, you can **sync** workers from **MSite** to the **Procore** system. Syncing workers creates **new worker profiles** in the **Procore** system for any **existing** MSite workers that are associated to **active sites**, which are **mapped to a project in Procore**, and/or, any workers who **do not** already have a **Procore Worker ID**.

Additionally, **MSite** can sync **worker deletion**, this will be done **automatically** and simply means that when a worker is **deleted in MSite**, that same worker will then be **deleted in Procore**. To enable this tick the **Auto Sync Worker Deletion** checkbox.

Worker Sync

Click 'Sync Workers Now' to create new worker profiles in Procore for any existing MSite workers that:

- are associated to active sites which are mapped to a project in Procore
- do not already have a Procore Worker ID

Sync Workers Now

☒ **Auto Sync Worker Deletion**

Procore workers will be deleted if a linked MSite worker is deleted

4. Syncing Transactional (Timecard) Data from MSite to Procore

When **any in or out transaction** is completed by a worker who has a **Procore Worker ID**, **MSite** will **automatically** send this data to Procore, allowing for **timecard entries** to be created in the **Procore** system.

To **enable Timecard** data to be synced between the two systems, tick the **Timecard Sync** checkbox.

Timecard Sync

☒ **Timecard Sync**

Uses MSite shift data (FILO) to create Timecard entries in Procore

FILO is a method of calculating shift length using First In and Last Out timestamps per worker, therefore ignoring breaks



+44 (0) 333 456 2001

PROCORE INTEGRATION

Enabling the Procore Integration

How to enable integration

5. Linking a Site within MSite to a Procore Project

To **sync workers** to **Procore**, you will be required to have sites on your **MSite instance** that are **linked** to a Procore project.


To **link a site** to a Procore project, open **Site Configuration**. You can do this by selecting **System** in the MSite toolbar on the left of the screen.

6.1 To create a **NEW** site select **Sites**, **Site Configuration** and then **Add Site**.




6.2 To link an **EXISTING SITE**, select **Sites**, **Site Configuration**, and then select the site from the drop-down box



 **Site Configuration**

Select Site

Please Select




PROCORE INTEGRATION

Enabling the Procore Integration

How to enable integration

- 7.** When you have added the new site **or** selected a site from the drop-down box.
Next select **Actions** and then **Edit**.



Site Configuration

Select Site: Site 01 - Liverpool

Site: Site 01 - Liverpool **Fingerprint**

Access Control

Distribution Client Machine: Liverpool Machine

Verbx Controller: Liverpool Controller **No Queue** **Last Sync: Never**

Door: Entry **Last Transaction: 07/03/2024 15:15**

Hand Reader: Entry Reader **No Queue**

Door: Exit **Last Transaction: 07/03/2024 15:16**

Misc Device: CardReader

Door: Accomodation Entry **Last Transaction: 07/03/2024 15:14**

Door: Accomodation Exit **Last Transaction: 07/03/2024 15:15**

Actions **Edit**



PROCORE INTEGRATION

Enabling the Procore Integration

How to enable integration

8. The **Edit Site Page** will open. From here you will be able to select the site in **Procore** you want to link to.

Once the site is selected select **Save**.

Procore Integration ?

Procore Project

Please Select

Procore Integration ?

Procore Project

Please Select
Chicago
London
Reference A
Reference B
Reference C
Reference D
Test Project A
The Bunker - Demo Project
Please Select

Edit Site

Site Contact Information (Public) ?

Site Name *

Site 01 - Liverpool

Enrolment Type *

Fingerprint

Site Group *

Default

Location

Liverpool

Manager

Nell Norman

Address

Postcode *

L13 1FB

Phone Number

0151123456

External ID ?

Notes

Site Opening Times (Public) ?

Site Open From *

09:00

Site Open Until *

17:00

Working Days *

All Selected

Site Delivery/Collection Information (Public) ?

Notice Period *

1

Days

Instructions

All deliveries to access site from J5 of M62. Avoid local traffic routes.

Auto Accept *

Off

Max Bookings per Slot *

2

Overboarding Options *

Warn

Site Advanced Information (HRS) ?

Distance Calculation Enabled

☐

HRS Project ID *

Use HTTP Distribution API

☐

Site Project Information (Public) ?

Project Start Date

Clear

Project End Date

Clear

Procore Integration ?

Procore Project

Please Select

Cancel

Save




PROCORE INTEGRATION

Enabling the Procore Integration


How to enable integration

9. How to create a new worker or link to an existing worker in Procore via MSite




If you are creating **new worker** or **editing an existing worker**. In the **Site Association** section of the **Worker's Profile**, you can add a new site or edit an existing site. When linking a worker to Procore, ensure the site you are linking to is one that is set up and **linked** to a **project** in Procore.

If the chosen site is linked to a **Procore project**, you should see the site in the **Procore Integration** Section:



10. Selecting **Create New Procore Worker** will pass the first and last name of the worker through to **Procore**. A worker will **automatically be created** in Procore, once you have saved the worker profile in MSite.

If a worker is **already created in Procore** select the **Link to Existing Procore Worker** option. A **list** of the Procore workers already created and associated with the selected project/site will now display. Find the worker and then click **Add**.



The final option, **Do not link to Procore**, simply means that by selecting this option, **no worker will be created in Procore**.

11. Your worker profile will now be **integrated with Procore**.

